

Cast smart tv to phone

☐

I'm not robot



reCAPTCHA

Continue



친구 ¹²어마
그리고
정사
무삭제판

딸과 새엄마의 대결



This photo you took is stunning, but do you know what else would surprise her? Design it on the big screen. Thanks to Smart View, you can connect a compatible Samsung device to Samsung Smart TV wireless mode. Cast photos, movies, presentations and games on the big screen to make them look bigger and better. Note: Possible screens and settings may vary depending on your wireless service provider, software version, and device model. Smart View is not available on all devices. Devices must be on the same Wi-Fi TV network to mirror the screen. As technology advances, so does the vocabulary. Now we all use terms like "mirror screen" or "casting" a lot and get really confused. What do they want to say? All you really need to know is that both allow you to cast movies, photos and other content from your phone to your smart TV. But if you want a bigger definition of the definition, we have it here. What is screen mirroring? The answer is in the name: screen mirroring. This function allows you to mirror what is on the screen on a larger screen, such as a smart TV. Exactly what is displayed on the phone will appear on the TV, whether it is a video menu, photo or settings. Every time you do something on your phone (like switch to another app), the action will also appear on the second screen. On Galaxy devices, the screen mirroring feature is called Smart View. You can easily create a screen that reflects the intelligent image just by tapping on the intelligent video icon and following a few simple steps. In the case of the iPhone, the screen mirroring function is called "AirPlay" and as in: mirror images, movies or other media. Using AirPlay is similar, but slightly different, to Smart Image. It doesn't matter what you have, it's a great way to share movies, photos or another phone right on your smart TV. The Galaxy smart view interface is irrelevant because the word can be used in many other situations. But when it comes to phones and TVs, "casting" means sending sounds and images in real time online. Some applications, like Netflix or YouTube, allow you to send movies from your phone directly to the big screen. Even if you don't have a smart TV, you can use a third-party streaming device like Chromecast or Amazon Firestick. During the broadcast, only the video or movie will be displayed on the screen. You can check the video on your phone. You can also close the application and do other things without interrupting the video if your phone is always connected. It is a very practical way to enjoy the film and the phone. If you have an iPhone or iPad, you can broadcast on TV using Airplay. Important: Make sure the TV is on and connected to the same Wi-Fi of the telephone network. Some televisions may require modifying the entries or activating the MyRRORING screen. Compatibility with the non-Samsung TV may vary or cannot be available. For more details, see the TV instructions manual. SmartView is not a downloadable application and is located in the quick setting panel. Make an excellent statement by watching photos or videos from your phone or tablet on your TV. You can also do the opposite and transmit the image of the TV on your phone or tablet! Open the quick setting panel, scrolling down with two fingers at the top of the screen. Then scroll and touch the Smart View icon. Note: If the Smart View icon is not displayed, try scrolling to the left. If it still does not appear, your device may not be compatible or added to the panel. Press your TV in the list of available devices. If necessary, enter the pin or leave access to finish the connection. The screen of your device will now appear on your TV. If you want to broadcast the TV screen on your phone or tablet and your TV supports it, it belongs to other devices → Telephone. To go back, it is other devices. When you have finished using Smart View, press the Smart View icon on the phone, so it's overwhelming. If you need help to customize the icons in the fast settings panel, see our guide. Before everyone can watch the show, make sure your computer and television have the right requirements. You will need: a computer compatible with Widi: Most recent computers provided with Windows 8 or Windows 10 will support Widi. The best way to know if your computer is compatible is to try the screen mirror. If your computer does not support Widi, you can always use a separate USB adapter. Miracast / Widi receiver on TV: Make sure your TV is equipped with a Miracast or Widi receiver. Otherwise, you can always use an external adapter. On your computer, click Start, then on settings, then on the devices. Click Bluetooth and other devices, then click Add Bluetooth or another device, then click the wireless display or the quay. When the name of the TV appears, click on it. If you are requested, select Activate on television. Once connected, click on PC. Now your computer screen will be reproduced on your TV. when you are!time for a mirror screen reflection, session. Start, then click "Settings" and finally click the devices. Click Bluetooth and other devices, then connect the TV. Delete the device and then click YES. You can also make a mirror copy of the phone or tablet on the TV screen using the SmartThings application. Using a phone or tablet, open the SmartThings application and select the TV you want to duplicate. Make sure the TV is open and connected to the SmartThings account. On the TV settings page, click other options (three vertical dots), and then click Smart View. If necessary, provide the TV with access to the device. Note. This feature may not be available in the SmartThings PC version. Note: Galaxy from Flip, Galaxy A and Galaxy J do not support HDMI output. If you can't wirelessly connect your phone or tablet to the TV, you can make a mirror copy of the screen with a DEX cable or USB-C cable on HDMI. Just connect the cable to the TV. In some models, the screen can automatically start reflection. In other cases, you may need to move the device screen to open the notification panel. Then tap the Samsung Dex notification with the content "click here to switch the screen". Now choose the right source on the TV, and everything that is displayed on the phone will appear on the TV. If you have a problem with the reflection of the phone or tablet, here are some tips: if your phone or tablet is not visible, you may need to obtain a permit from the TV. Restart the device and TV, and then try to connect again. When displaying on the TV, remember to choose resolution. You should also try to check the availability of software updates on your devices. If the problem is repeated, restore the phone or tablet to the factory settings. On the Samsung TV you can withdraw permission to access the device on the TV. From settings on the TV to general, and then go to the manager of external devices. Go to Device Connect Manager and then select a notification of access. When using Smart View, set automatic connecting to the device. On the screen of device connection manager, you can also choose a list of devices to manage devices connected to the TV. If the screen is still closing, change the time settings in front of the screen. Search and select an element of a trip on the screen in the settings. From there, enter the settings so that the phone or tablet is open longer. If the Smart View menu is reduced to the icon, tap the Smart View icon on your phone or tablet. Smart View control menu!t only appears on the connected device. If the image of your device on the screen seems small, you can increase it a little by changing the aspect ratio. On the phone or tablet, click the Smart View icon and then on other options (three vertical dots). Click Settings and then on the Page Ratio. From there you can choose the desired aspect ratio. Most TVs look best with 16: 9 aspect ratio. Thank you for your opinion! © 2023 Samsung Electronics America, Inc. Samsung, Samsung Galaxy and Family Hub are registered trademarks of Samsung Electronics Co., Ltd. All other trademarks, products and services and their trademarks, names and logos are the property of the relevant owners. The above content is used only for entertainment and information purposes. See the user manual for more information. All information in this document may change without warning. Samsung is not responsible for any random or subsequent damage incurred in connection with the use or reliance on the content contained here. Display content from your Android mobile device on the TV while sharing Android screen. This feature is only available on Android 8.0 or later devices. Step 1: We are starting to make sure your Android device has enough energy, turn off energy saving or energy saving mode. Important: To allow your Android device to send a screen, enable the Google Play permissions to the microphone. Click Settings on the Android device. Scroll down and click Google Play permissions. Find the "microphone" switch in authorization. Step 2: Sending screen from Android Make sure your mobile phone or tablet is connected to the same Wi-Fi network as the Chromecast device. Open Google Home. Touch and hold the device tile to share the screen with. Click the Live Broadcast screen. Step 3: Adjust the volume of Android screen to open Google Home. Click Media to edit the volume. Step 4: Stop screen sharing from Android Make sure your mobile phone or tablet is connected to the same Wi-Fi network as the Chromecast device. Open Google Home. Tap and hold the tile to stop the mirroring of the device. .

